Sounds Virtual Inc 920 Yonge st, Suite 810 Toronto On M3C 4W7 416 968 7155 - Toll free: 1 855 305 9937

Installing CAN-8 as a Service

These instructions apply to the following OS:

Windows Vista, Windows 7, Windows server 2003, Windows server 2008 & 2008 R2, Windows server 2012 & 2012 R2, Windows 2016 and windows 2019.

Before you start

The following instructions assume that the CAN-8 application is operating in the C:\SVSYS folder. If this is not the case please modify these instructions accordingly.

To install CAN-8 as a service, the following files will be required:

- <u>SRVANY.EXE</u>
- <u>INSTSRV.EXE</u>

For your convenience, we bundled them in the "FILES" folder included in this distribution package:

- 1. Create a folder in the **C:\windows** folder and call it "TOOLS" (i.e. C:\WINDOWS\TOOLS\)
- 2. Copy both these files to it.

STEP 1: Create the service.

- 1. Start a command prompt and change to the directory C:\windows\tools
- 2. If you are using Windows 7, Windows server 2008, Windows server 2012 or any operating system more recent than these, make sure to right click on the command prompt icon and select "*Run As Administrator*".
- 3. Type the following line to create the CAN8srv Service:

instsrv CAN8srv c:\windows\tools\srvany.exe



4. Once Windows NT has reported that the service has been successfully created the parameters will need to be modified.

STEP 2 – Modify the parameters:

- 1. Exit the command prompt and then open the Registry Editor START->RUN->REGEDIT.EXE
- 2. Under

KEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\Services\CAN 8srv: create a '**Parameters**' key



3. In the 'Parameters' key, create an "**Application**" <u>string value</u> of type REG_SZ and specify there the full path of your application executable (including the extension). *For example: C:\SVSYS\NTSERVE.exe*

Favorites Help		
D - 🕕 BTHPORT 🛛 🖌	Name	Туре
b - 🎍 bthserv A - 📕 CAN8srv	(Default)	REG_SZ
Parameters		- 12
>- 🍌 cdfs	New 🕨	Key
🛛 - 🍌 cdrom		String Value
CertPropSvc		Stillig value
🔉 – 📙 circlass –		Binary Value
- CLFS		DWORD (32-bit) Value
clr_optimization_v2.0.50727_3. ≡		OWORD (64-bit) Value
		Marking Contraction
cmdide	9	Multi-String Value
CNG		Expandable String Value
Complete		

Favorites Help		
BTHPORT	~	Name
> 🦂 bthserv		ab (Default)
🚛 🔒 CAN8srv		ab Application
Parameters		Application

ab) (Default)	REG_SZ	(val
ab Application	REG_SZ	
Edit String		x
Value name:		
Application		
Value data:		
C:\SVSYS\NTSERVE.EXE		
	ОК Са	ancel
C:\SVSYS\NISERVE.EXE	ОК Са	ancel

4. In the 'Parameters' key, create an "AppDirectory" <u>string value</u> of type REG_SZ and specify the parameters for your application directory.

For Example: C:\Svsys

REG_SZ	(value not set)
REG_SZ	C:\SVSYS\NTSERVE.EXE
REG_SZ	
OK Can	cel
	REG_SZ REG_SZ REG_SZ

5. Because Microsoft delays the start of certain driver processes on their Windows server products at startup, the drivers for the serial port may not be completely initialized by the time the service control manager starts the CAN-8 service. If such is the case, the CAN-8 application will be unable to communicate with the authorization device and the service will fail.

To prevent this, if your version of CAN-8 dates <u>April 2004 or later only</u>, in the 'Parameters' key, create an 'AppParameters' <u>string value</u> of type REG_SZ and add the following string: *-w 10*

Name		Туре	Data
ab (Default)		REG_SZ	(value not set)
ab Application		REG_SZ	C:\SVSYS\NTSERVE.EXE
ab AppDirector	у	REG_SZ	C:\SVSYS
an AppParame	ters	REG_SZ	
	alue name: ppParameters alue data: w 10	ОК	Cancel

This will force the NTSERVE program to wait 10 seconds prior to attempting communication with any other device on the server.

Once the parameters have been successfully modified the service must be started.

STEP 3 – Starting the CAN-8 service:

- 1. Open the service console
- 2. Control Panel -> Administrative Tools -> Services
- 3. Select CAN8srv in the list of services.
- 4. Right click and select start.

TWA CONTRACTOR OF THE OWNER		
CAN8srv		Automatic
Certificate Propa	Start	Manual
CNG Key Isolatio	Stop	Manual
🔍 COM+ Event Sys	Pause	Automatic

- 5. If the service is not set to "automatic", right click on the service name, and then select properties,
- 6. You can change the startup type as illustrated below.

ieneral	Log On	Recovery	Dependen	cies	
Service	name:	CAN8srv			
Display	name:	CAN8srv			
Descrip	tion:				*
Path to	executabl	le:			
Path to C:\wind	executabl lows\tools	le: \srvany.exe	Ţ	Z	
Path to C:\wind Startup	executabl lows\tools type:	/ /srvany.exe Automatic		7	 -
Path to C:\wind Startup <u>Help ma</u>	executabl lows\tools type: e configure	le: Srvany.exe Automatic	tup options	2	 •
Path to C:\wind Startup <u>Help ma</u> Service	executabl lows\tools type: <u>e configure</u> status:	le: Srvany.exe Automatic e service star Stopped	tup options	2	 •

This concludes this procedure. If you have any question regarding this procedure or need assistance at any point during the installation, please contact us at <u>support@can8.com</u>